

COMPOUND BLOCK AND TACKLE (PARALLEL)

MED 11.05



Material

Item-no.	Qty.	Description
DS090-3K	1	Claw base "Sepp", 260 x 220 mm
DS093-04	1	Sliding saddle "Sepp", H=40 mm
DS095-3K	1	Bosshead cross-pattern, demo 03
DS201-00	1	Support rod, round, L=1000 mm, D=12 mm
DS203-1S	1	Support with hook
DG110-1G	1	Pointers for rods, pair
DM210-2P	1	Parallel pulley block, pulley D=100 mm
DG200-1S	1	Cord, D=1.7 mm, L=5 m
DM121-7A	1	Weight on hook 1 kg, profi
DM121-6A	1	Weight on hook 500 g, profi
DM725-ND	1	Newtonmeter "inno" 20 N / 2000 g
P3120-5B	1	S-shaped assembly platform

BLOCK AND TACKLE (PARALLEL)


Purpose

To demonstrate the effect of a parallel compound block and tackle consisting of four pulleys.

Preparation

Insert the 1000 mm support rod into the sliding saddle of the claw base; then mount the sliding saddle "Sepp" on the end of the claw base.

The weighing bar of the Newtonmeter is mounted in this sliding saddle.



Mount the bosshead at a height of 90 cm on the support rod; the support with hook is fixed to this bosshead.

Cut off a 230 cm piece of the cord and make loops at both ends of the cord; the remaining length after making the loops should be around 220 cm.

Mount the „block and tackle“ - block with 2 hooks on the support with hook and hang the cord to the bottom hook.

Wind the cord around the pulleys as shown on the image and hang the other end of the cord on the hook of the weighing bar.

Place the Newtonmeter on the S-shaped assembly platform for better visibility, set the measuring range of the Newtonmeter to „N“ (Newton), turn it on afterwards and tare if required (set to 0).



BLOCK AND TACKLE (PARALLEL)

Experiment 1

Load one or more weights on the compound block and tackle.

Result

Approximately only a quarter of the force of weight is required to hold the mass.

The friction of the pulleys causes a small loss of force, thus the force of weight will be a little less than a quarter of the total force of weight..

Experiment 2

Adjust the upper pointer so that it marks the bottom end of the pulley.

Remove the weighing bar from the sliding saddle and raise it by 50 cm approximately; thus the weight moves down.

Measure the two paths with a ruler or tape measure and compare them.

Result

With an (force) effort of a quarter of the attached weight four times the way is needed.

Bei einem Kraftaufwand von einem Viertel des angehängten Gewichts benötigt man den vierfachen Weg.


$$F \times s = \frac{F}{4} \times 4s$$

The mass is distributed on the 4 pulleys; only the corresponding fraction of the force has to be exerted by one pulley.

The change of direction of the force can also be observed.

Note

The most common embodiment of a compound block and tackle can be found for example with cranes when lifting heavy loads. Cranes that operate with very heavy loads usually use more than four pulleys.



BLOCK AND TACKLE (PARALLEL)

The most common embodiment of a compound block and tackle can be found for example with cranes when lifting heavy loads. Cranes that operate with very heavy loads usually use more than four pulleys.